

USB-3100 Series

The USB-3100 Series includes the USB-3101, USB-3102, USB-3103, USB-3104, USB-3105, USB-3106, USB-3110, USB-3112, and USB-3114 devices.

Analog output

Analog output functions and methods supported

UL:	cbAOut (), cbAOutScan ()
UL for .NET:	AOut (), AOutScan ()

Nombre de channel max que l'on souhaite utiliser.
Le compte commence à 0 et finit à 3 avec le USB-3101
(bien 4 channels output analogique)

Analog output argument ranges

Options	SIMULTANEOUS (cbAOutScan () / AOutScan () only)
HighChan	USB-3101, USB-3102, and USB-3110: 0 to 3 USB-3103, USB-3104, and USB-3112: 0 to 7 USB-3105, USB-3106, and USB-3114: 0 to 15
Rate	Ignored
Count	HighChan – LowChan + 1 max
Range	Ignored - Not programmable; selectable for BIP10VOLTS (± 10 V), UNI10VOLTS (0 to 10 V), or MA0TO20 (0 to 20 mA) via <i>InstaCal</i> USB-3102, USB-3104, USB-3106: Also selectable for MA0TO20 (0 to 20mA) via <i>InstaCal</i>
DataValue	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 16.)

Digital I/O

Configuration functions, methods, and argument values supported

UL:	cbDConfigBit (), cbDConfigPort ()
UL for .NET:	DConfigBit (), DConfigPort ()
PortNum	AUXPORT
PortType	AUXPORT

Port I/O functions, methods, and argument values supported

UL:	cbDOut (), cbDIn ()
UL for .NET:	DOut (), DIn ()
PortNum	AUXPORT
DataValue	0 to 255 for AUXPORT

Bit I/O functions, methods, and argument values supported

UL:	cbDBitIn (), cbDBitOut ()
UL for .NET:	DBitIn (), DBitOut ()
PortType	AUXPORT
BitNum	0 to 7 on AUXPORT

Counter I/O

Counter I/O functions and methods supported

UL: `cbCIn () *`, `cbCIn32 ()`, `cbCLoad () **`, `cbCLoad32 () **`

UL for .NET: `CIn () *`, `CIn32 ()`, `CLoad () **`, `CLoad32 () **`

***Although `cbCIn ()` and `CIn ()` are valid for use with this counter, `cbCIn32 ()` or `CIn32 ()` may be more appropriate, since the values returned may be greater than the data types used by `cbCIn ()` and `CIn ()` can handle.**

****`cbCLoad ()`, `cbCLoad32 ()`, `CLoad ()` and `CLoad32 ()` only accept `Count=0`. These functions are used to reset the counter.**

Counter I/O argument values

CounterNum 1

Count $2^{32}-1$ when reading the counter.

LoadValue 0 when loading the counter.

`cbCLoad ()` and `cbCLoad32 ()` / `CLoad ()` and `CLoad32 ()` are only used to reset the counter for this board to 0. No other values are valid.

The “[Basic signed integers](#)” guidelines on page 140 apply when using `cbCIn ()` or `CIn ()` for values greater than 32767, and when using `cbCIn32 ()` or `CIn32 ()` for values greater than 2147483647.

RegNum LOADREG1

Hardware considerations

Scan options

The `SIMULTANEOUS` scan option can only be used with `cbAOutScan ()` / `AOutScan ()`.

Simultaneous mode

Set the direction of the SYNCLD pin (pin 49) with the **Simultaneous Mode** option in *InstaCal* to be either Master (output) or Slave (input).

- Specify the `SIMULTANEOUS` scan option and set the Simultaneous Mode option to **Master** to output the internal D/A LOAD signal on the SYNCLD pin.
- Specify the `SIMULTANEOUS` scan option and set the Simultaneous Mode option to **Slave** to configure the SYNCLD pin to receive the D/A LOAD signal from an external source. Output channels are updated simultaneously when the SYNCLD receives the signal.

In slave mode, analog outputs may either be updated immediately or when a positive edge is seen on the SYNCLD pin (this is under software control.) The SYNCLD pin must be at a low logic level for DAC outputs to update immediately. If an external source is pulling the pin high, no update will occur.

When you do not specify `SIMULTANEOUS`, the analog outputs are updated in sequential order, and the SYNCLD pin is ignored.

External current limiting may be required for high drive devices (USB-3110, USB-3112, USB-3114)

The voltage outputs on the USB-3110, USB-3112, and USB-3114 incorporate high-drive current output capability. The high drive current outputs allow each of the voltage outputs to sink/source up to 40 mA (maximum) of load current.

The voltage outputs should not be kept in a short-circuit condition for longer than the specified 100 ms. For those applications that may potentially exceed the 40 mA maximum current limit or the 100 ms short-circuit condition, external current limiting must be used to prevent potential damage to the USB-3100 series device.

Simultaneous update of voltage and current outputs (USB-3102, USB-3104, USB-3106)

Each voltage output channel on the USB-3102, USB-3104, and USB-3106 has an associated current output. The voltage and current outputs are grouped as channel pairs. Each D/A converter output controls a voltage and current channel pair simultaneously. When you write to a voltage output, its associated current output is also updated. Each channel pair can be updated individually or simultaneously.

Each voltage/current channel pair can be updated individually or simultaneously. Leave each pair of unused voltage and current outputs disconnected.

Miscellaneous functions and methods supported

UL: `cbFlashLED()`

UL for .NET: `FlashLED()`

Causes the USB LED on a USB device to blink.

When you have several USB devices connected to the computer, use these functions to identify a particular device by making its USB LED blink.